

simplex Meeting & simplex Integration

Index

1	Overview	2
2	Prerequisites	2
3	Enable simplex Meeting & simplex integration for a simplex Meeting account	2
4	Enable simplex Meeting & simplex integration as a Meeting Organizer	3
5	Enable broadcasting/webcasting of a meeting	3
6	Enable broadcasting/webcasting in the meeting	4

1 Overview

With the integration of the two systems [simplex Meeting](#) & [simplex](#), another big step has been taken to use the possibilities across systems.

The *simplex Meeting* & *simplex* integration allows you to webcast your meeting or webinar automatically and very easily, directly from *simplex Meeting*; without much preparation.

In the meeting itself you can just start the webcast and the content of the meeting will be streamed live under the selected *simplex* project. With this integration you have almost unlimited viewers enabled.

2 Prerequisites

The *simplex Meeting* & *simplex* integration needs to be configured and activated for each *simplex Meeting* White Label instance separately. Furthermore, the *simplex Meeting* White Label Account Customer must have also a *simplex* account.

Please contact us if you do not have this feature enabled in your *simplex Meeting* White Label Account or if you do not have a *simplex* account.

Currently, only the **meeting organizer** can broadcast/webcast a meeting. Additionally, the meeting organizer needs to join the meeting in **Google Chrome**.

3 Enable simplex Meeting & simplex integration for a simplex Meeting account

Once you have this feature available you can activate it for specific accounts. By default, accounts do not have access to this feature. Go to "**Account management**", select an account and enable this feature for that account there.

My Company

Update account

Account type: Professional

Optional account id: _____

Optional company/account name: My Company

Optional comment: Some comment

Number of months to add: _____
Paid until: August 17, 2021
How many additional months has this customer paid for? Use negative numbers to remove month.

Auto-extend account before it expires?

Enable broadcasting?

Number of meeting rooms to add or remove: _____
Current number of meetings rooms: 1
One meeting room is equal to one concurrent meeting. Every account needs at least 1 meeting room. Charges occur for each meeting room that you sell.

4 Enable simplex Meeting & simplex integration as a Meeting

Organizer

Once you have this feature available you can activate the integration in your simplex Meeting account under "Settings" > "simplex Webcasting (Broadcasting) integration" by entering your simplex author login details and the confirmation by means of the button "ENABLE SIMPLEX INTEGRATION".

Simplex Webcasting integration

When you schedule a meeting you can select a Simplex Project for broadcasting.

Important information: You need a Simplex author account to create Simplex projects.

Simplex author username	<input type="text" value="test@author"/>
Simplex author password	<input type="password" value="....."/>

The integration can also be deactivated here at any time.

Simplex Webcasting integration

When you schedule a meeting you can select a Simplex Project for broadcasting.

Important information: You need a Simplex author account to create Simplex projects.

You are currently authenticated

5 Enable broadcasting/webcasting of a meeting

Once enabled for an account and under the account settings of the meeting organizer broadcasting/webcasting can be enable for specific meetings.

While creating the meeting, select an existing project from your *simplex* author account or automatically create a new project under your *simplex* author account. Following project details will be automatically added to the meeting.

1. RTMP streaming server address (server URL)
2. RTMP streaming key/secret (stream name)


With this information a meeting is configured for broadcasting/webcasting:

☰ Schedule meeting ⌂


Documents	Pre-upload documents for the meeting <input type="button" value="📎"/>	Document store <input type="button" value="▼"/>
Participant email address to join the meeting	Optional <input type="button" value="▼"/>	
Meeting permissions	All permissions (Default) <input type="button" value="▼"/>	
Video resolution	320x240 - 4:3 (recommended) <input type="button" value="▼"/>	
Broadcast meeting	<input checked="" type="checkbox"/>	
Simplex project	Select a Simplex project <input type="button" value="▼"/>	<input type="button" value="ADD NEW PROJECT"/>
Requirements to join meeting	None <input type="button" value="▼"/>	
Meeting password (optional)	<input type="text"/>	

6 Enable broadcasting/webcasting in the meeting

A meeting that can be broadcasted will have a **“Start Broadcasting”** button available for the meeting organizer. Note that this button currently only shows up in **Google Chrome**.




Pressing on that button opens a browser popup. Select the **“Chrome Tab”** and find the tab that says **“Broadcast: select this tab”** and then click on **“Share”**. This starts broadcasting your session to the **simplex Media Streaming Server**.



Your meeting will now be broadcast live under the *simplex* project link you created.

simplex



If you want to stop the streaming session you have to click on **“Stop Broadcasting”** in your meeting.